OpenVMS/Hanyu VAX Version 7.2 Installation Guide

Order Number: AA-PZCLF-TE

May 1999

This document contains installation information for the OpenVMS/Hanyu VAX Version 7.2 operating system.

Revision/Update Information: This is a new manual.

Software Version: OpenVMS/Hanyu VAX Version 7.2

Compaq Computer Corporation
Asia Region

First Printing, May 1999

Compaq Computer Corporation makes no representations that the use of its products in the manner described in this publication will not infringe on existing or future patent rights, nor do the descriptions contained in this publication imply the granting of licenses to make, use, or sell equipment or software in accordance with the description.

Possession, use, or copying of the software described in this publication is authorized only pursuant to a valid written license from Compaq or an authorized sublicensor.

Compaq conducts its business in a manner that conserves the environment and protects the safety and health of its employees, customers, and the community.

© Compaq Computer Taiwan Limited 1999. All rights reserved.
Printed in Singapore

The following are trademarks of Compaq Computer Corporation: Alpha, AlphaGeneration, AlphaServer, AlphaStation, Bookreader, CDA, CI, Compaq DEC, DEC Ada, DEC BASIC, DEC Fortran, DEC Notes, DECdirect, DECdtm, DECevent, DECforms, DECmigrate, DECnet, DECpresent, DECterm, DECthreads, DECwindows, DIGITAL, HSC, HSC40, HSC70, HSJ, HSZ, InfoServer, LAT, LinkWorks, ManageWORKS, MSCP, OpenVMS, OpenVMS Cluster, PATHWORKS, POLYCENTER, RRD42, RZ, StorageWorks, TeamLinks, TMSCP, TURBOchannel, UETP, VAX, VMS, XUI, and the Compaq logo.

The following are third-party trademarks:

Microsoft, Windows, Windows NT, and MS–DOS are registered trademarks of Microsoft Corporation.

Motif are registered trademarks of the Open Software Foundation, Inc.

PostScript is a registered trademark of Adobe Systems Incorporated.

All other trademarks and registered trademarks are the property of their respective holders.

This document was prepared using VAX DOCUMENT Version 2.1.

Contents

Preface v

1 Preparing for OpenVMS/Hanyu VAX Installation

1.1 Software Prerequisites 1–1
1.1.1 Required Base Operating System 1–1
1.1.2 Required Layered Product 1–1
1.2 Prerequisite Hardware 1–2
1.3 License Registration 1–2
1.4 Installation Procedure Requirements 1–2
1.4.1 Time 1–2
1.4.2 Privileges 1–2
1.4.3 Disk Space 1–3
1.5 Resources Requirement 1–3
1.5.1 System Parameters 1–3
1.5.2 Process Account Quotas 1–4
1.5.3 Backing Up Your System Disk 1–5
1.6 Warning on OpenVMS/Hanyu VAX Upgrades 1–5
1.7 Examining VAXVMSSYS.PAR File 1–6

2 Installation Options

2.1 Asian Printing Support Sub-Kit 2–1
2.2 DECwindows Motif/Hanyu Fonts 2–1

3 Installing OpenVMS/Hanyu VAX

3.1 The Installation Procedure 3–1
3.1.1 Invoking VMSINSTAL 3–1
3.1.2 Installation Questions 3–2
3.1.3 Informational Messages 3–6
3.1.4 Before completing Installation Procedure 3–6
3.1.5 Completing the Installation Procedure 3–6

3.2 Error Recovery 3–6

4 After Installing OpenVMS/Hanyu VAX

4.1 Rebooting The System 4–1
4.2 Running the Installation Verification Procedure 4–2
4.3 Updating Individual Compilers Libraries 4–2
4.4 Determining and Reporting Problems 4–3

A OpenVMS/Hanyu VAX Sample Installation

B OpenVMS/Hanyu VAX Sample Installation Verification Procedure

C OpenVMS/Hanyu VAX Software Components and Defined System Logical Names

Tables

1–1 Disk Space Requirement 1–3
1–2 System Parameter Requirement 1–3
1–3 Process Account Quotas Requirements 1–4
C–1 Component File List C–1
C–2 Defined System Logical Names C–8

Preface

Purpose of This Guide

This guide describes how to install OpenVMS/Hanyu VAX Version 7.2 (hereafter referred to as OpenVMS/Hanyu VAX) on OpenVMS VAX Version 7.2.

Keep this document with your distribution kit. You will need it to install maintenance updates or to reinstall OpenVMS/Hanyu VAX for any other reasons.

Intended Audience

This guide is intended for OpenVMS/Hanyu VAX system manager.

It is assumed that users of this guide are experienced in upgrading the OpenVMS operating system and are familiar with:

- System Management
- VMSINSTAL

Associated Documents

- *OpenVMS/Hanyu Version VAX 7.2 Release Notes*
- *OpenVMS VAX Version 7.2 Upgrade and Installation Manual*
- *DECprint Supervisor for OpenVMS Release Notes*
- *DECprint Supervisor for OpenVMS Software Installation Guide*
- *OpenVMS License Management Facility Manual*
- OpenVMS Documentation set
- OpenVMS/Hanyu Documentation set
- *Asian Printing Support for OpenVMS Version 1.0 Release Notes*
- *Asian Printing Support for OpenVMS Version 1.0 Installation Guide*

Document Structure

This guide is organized as follows:

- Chapter 1 describes the preparations and requirements necessary for installing OpenVMS/Hanyu VAX.
- Chapter 2 describes the installation options available.
- Chapter 3 describes how to install OpenVMS/Hanyu VAX.
- Chapter 4 describes the steps to proceed after OpenVMS/Hanyu VAX is installed.
- Appendix A contains a log of a sample installation of OpenVMS/Hanyu VAX.
- Appendix B contains a log of a sample execution of Installation Verification Procedure of OpenVMS/Hanyu VAX.
- Appendix C contains a list of files and logical names created or modified by this installation procedure.

Conventions

The following conventions are used throughout this guide.

Convention	Meaning
KEY	Means pressing the key named inside the box.
Return	Carriage return.
CTRL	The phrase CTRL/x indicates that you must press key labeled CTRL while you simultaneously press another key. For example, CTRL/C, CTRL/Y and CTRL/O.
. . .	Vertical ellipsis in an example means that information not directly related to the example has been omitted.
[ ]	In format descriptions, brackets indicate that whatever is enclosed within the brackets is optional; you can select none, one or all of the choices.
UPPERCASE	Indicates logical, file and command names.

1

Preparing for OpenVMS/Hanyu VAX Installation

This chapter discusses the preparations and requirements necessary for installing OpenVMS/Hanyu VAX.

1.1 Software Prerequisites

1.1.1 Required Base Operating System

OpenVMS/Hanyu VAX Version 7.2 requires the OpenVMS VAX Version 7.2 operating system. OpenVMS VAX Version 7.2 must be installed and running on the system before OpenVMS/Hanyu VAX Version 7.2 is installed.

OpenVMS/Hanyu VAX Version 7.2 also requires the XPG4 locale database for the DEC Hanyu Character Set. This database is in the VMSI18N072 kit that is provided on the same media as the OpenVMS VAX Version 7.2 operating system. It is not installed during the installation of OpenVMS VAX Version 7.2. To install this database, install the VMSI18N072 kit using VMSINSTAL procedure after the installation of OpenVMS VAX Version 7.2 is complete. Be sure to answer YES to the question "Do you want Chinese support?"

If you are planning to set up an international environment in your system, you must select other locale databases during the installation of the VMSI18N072 kit. You can install the locale databases after the VMSI18N072 kit is installed if necessary. Please refer to the *OpenVMS VAX Version 7.2 Upgrade and Installation Manual* for details.

1.1.2 Required Layered Product

To enable World-Wide PostScript printing subsystem feature provided by OpenVMS/Hanyu VAX Version 7.2, it requires to install DECprint Supervisor for OpenVMS (DCPS) Version 1.0C or higher. For details on the installation of DECprint Supervisor for OpenVMS, please refer to *DECprint Supervisor for OpenVMS Release Notes* and *DECprint Supervisor for OpenVMS Software Installation Guide*.

1.2 Prerequisite Hardware

OpenVMS/Hanyu VAX Version 7.2 requires the following hardware:

- Any valid VAX configuration supported by OpenVMS VAX Version 7.2
- VT382-D Chinese terminal

1.3 License Registration

You must register and load your license for OpenVMS/Hanyu VAX Version 7.2 *before* you start the installation in order to run the Installation Verification Procedure (IVP) and use the software.

To register a license under OpenVMS, first log in to the system manager's account, SYSTEM. You then have a choice of two ways to perform the registration:

- Invoke the SYS$UPDATE:VMSLICENSE.COM procedure. When it prompts you for information, respond with data from your License PAK.
- At the DCL prompt, enter the LICENSE REGISTER command with the appropriate qualifiers that correspond to License PAK information.

For complete information on using LMF, see *OpenVMS License Management Utility Manual*.

1.4 Installation Procedure Requirements

The following sections discuss various requirements for installing OpenVMS /Hanyu VAX.

1.4.1 Time

The installation takes approximately 10 to 45 minutes, depending on your system configuration and the options you select during the installation.

1.4.2 Privileges

To install OpenVMS/Hanyu VAX, you must log in to the system manager's account or an account that has the SETPRV privilege.

1.4.3 Disk Space

Installing OpenVMS/Hanyu VAX requires certain amount of free storage disk space during the installation. Once installed, less disk space will be required. Table 1–1 summarizes the disk space requirement for OpenVMS/Hanyu VAX Version 7.2.

Table 1–1 Disk Space Requirement

Maximum disk space utilization during installation	
with DECwindows Motif /Hanyu fonts	119,900 blocks
Without DECwindows Motif /Hanyu fonts	101,300 blocks
Net disk space utilization after installation	
with DECwindows Motif /Hanyu fonts	86,400 blocks
without DECwindows Motif /Hanyu fonts	86,000 blocks

1.5 Resources Requirement

To determine the number of free disk blocks on the current system disk, enter the following command at the DCL prompt:

```
$ SHOW DEVICE SYS$SYSDEVICE
```

The available free blocks must be greater than or equal to the maximum disk space required for installation, i.e. 119,900 blocks or 101,300 blocks, depending on whether you are going to install DECwindows Motif /Hanyu fonts or not.

1.5.1 System Parameters

Installing OpenVMS/Hanyu VAX requires certain system parameter available resources. Table 1–2 lists the minimum required system parameter values for installation.

Table 1–2 System Parameter Requirement

Parameter name	Minimum value
GBLPAGES	3,000 pages
GBLSECTIONS	40 sections

To determine the number of free global pages and global sections on the system: first you can use the SYSGEN utility to check the current value of global pages and global sections. For example:

```
$ MCR SYSGEN
SYSGEN> SHOW GBLPAGES
SYSGEN> SHOW GBLSECTIONS
SYSGEN> EXIT
```

Then, enter the following command at DCL prompt to display global pages and global sections usage on the system.

```
$ INSTALL LIST /GLOBAL /SUMMARY
```

The difference of the two figures must be greater than or equal to the minimum values required for installation.

1.5.2 Process Account Quotas

The account you use to install OpenVMS/Hanyu VAX must have sufficient quotas to enable you to perform the installation. Table 1–3 summarizes the process account quotas required for the installation account.

Table 1–3 Process Account Quotas Requirements

Account Quota	Value
ASTLM	40
BIOLM	40
BYTLM	32768
DIOLM	40
ENQLM	200
FILLM	300

The installation procedure checks your account quotas at the beginning of the installation. For each account quota that is below the minimum requirement, the installation procedure displays a message that shows your account quota and the minimum requirement. If any of your account quotas is indeed below the minimum requirement, the installation procedure will ask whether you want to continue with the installation. You can answer YES to continue but the installation may or may not complete successfully. Alternatively, you can answer NO or press the Return key to abort the installation. Then you can correct the account quotas and restart the installation.

User account quotas are stored in the file SYSUAF.DAT. You can use the Authorize utility to verify and change user account quotas. First set your default directory to SYS$SYSTEM and then run AUTHORIZE:

```
$ SET DEFAULT SYS$SYSTEM
$ RUN AUTHORIZE
UAF>
```

At the Authorize utility prompt (UAF>), use the SHOW command with an account name to check a particular account. For example:

```
UAF> SHOW SYSTEM
```

To change the quota, use the MODIFY command at the UAF> prompt. For example, to change the FILLM quota for the SYSTEM account and then exit, you can type the following:

```
UAF> MODIFY SYSTEM/FILLM=300
UAF> EXIT
```

After you exit from the Authorize utility, the OpenVMS operating system displays messages indicating whether or not changes were made. Once the changes have been made, the owner of the altered account must log out and then log in again for the new quotas to take effect.

For more information on modifying account quotas, see the description of the Authorize utility in the OpenVMS Documentation Set.

1.5.3 Backing Up Your System Disk

At the beginning of the installation, VMSINSTAL procedure asks if you have backed up your system disk. Compaq recommends that you do a system disk backup before installing any software.

Use the backup procedures that have been established at your site. For details on performing a system disk backup, see the section on Backup utility in the OpenVMS documentation set.

1.6 Warning on OpenVMS/Hanyu VAX Upgrades

OpenVMS/Hanyu VAX can only be installed on the corresponding version of OpenVMS VAX. When you upgrade OpenVMS/Hanyu VAX system, you have to:

1. Upgrade the base OpenVMS VAX system.
2. Then, install the OpenVMS/Hanyu VAX kit on the upgraded base OpenVMS VAX system.

To upgrade the base OpenVMS VAX system, you have to:

1. Remove the HSY$STARTUP.COM startup command procedure of OpenVMS/Hanyu VAX from the system startup sequence. In other words, SYS$STARTUP:HSY$STARTUP.COM should be taken out from

SYS$MANAGER:SYSTARTUP_VMS.COM site specific startup command procedure or removed from the SYSMAN utility as a startup file.

2. Execute the command procedure @HSY$SYSTEM:RECOVER.COM to restore from OpenVMS/Hanyu VAX system to OpenVMS VAX system. RECOVER.COM will replace some of the localized images with the original images.

3. Reboot the system.

Note

If you are upgrading from OpenVMS/Hanyu VAX Version 6.1 and have not applied the AVMSMUP01_061 mup kit, you *must* reset the SYSGEN parameter LGI_CALLOUTS to 0 *before* rebooting the system, as follows:

```
$ RUN SYS$SYSTEM:SYSMAN
 SYSMAN> PARAMETER USE CURRENT
 SYSMAN> PARAMETER SET LGI_CALLOUTS 0
 SYSMAN> PARAMETER WRITE CURRENT
 SYSMAN> EXIT
```

Otherwise, you may not be able to log into your system after reboot.

4. After the system has been rebooted, upgrade the base OpenVMS VAX operating system.

1.7 Examining VAXVMSSYS.PAR File

Before you begin an installation for OpenVMS/Hanyu VAX, be sure the file protection of the VAXVMSSYS.PAR file stored in SYS$SYSTEM directory is "System:RWED,Owner:RWED, Group:RE,World:RE". If it is incorrect, you need to change the file protection of the VAXVMSSYS.PAR file with the following command.

```
$ SET FILE /PROTECTION=(S:RWED, O:RWED, G:RE, W:RE) -
_$ SYS$COMMON:[SYSEXE]VAXVMSSYS.PAR
```

2
Installation Options

This chapter describes the options provided with the installation.

2.1 Asian Printing Support Sub-Kit

There is a separate sub-kit called ASPS010 provided in the media of OpenVMS /Hanyu VAX Version 7.2. It is used to install the Asian Printing Support for OpenVMS Version 1.0. If you want to have high quality Chinese printing capabilities, please install this sub-kit after the installation of OpenVMS /Hanyu VAX Version 7.2. For details on the installation and features of Asian Printing Support, please refer to *Asian Printing Support for OpenVMS Version 1.0 Installation Guide* and *Asian Printing Support for OpenVMS Version 1.0 Release Notes*.

Note

High quality Chinese printing is only supported with the installation of DECprint Supervisor for OpenVMS (DCPS) Version 1.0C or higher. That is, in addition to the Asian Printing Support sub-kit, you must install DCPS V1.0C or higher if you want to have Chinese printing supported.

2.2 DECwindows Motif/Hanyu Fonts

During the installation of OpenVMS/Hanyu VAX Version 7.2, you have the option to install DECwindows Motif/Hanyu fonts. If you are planning to install DECwindows Motif/Hanyu or above, you must install this option; otherwise you do not need to install this option. If you want to install the fonts after OpenVMS/Hanyu VAX Version 7.2 is installed, you must re-install the OpenVMS/Hanyu VAX Version 7.2 by restoring the system to OpenVMS VAX first. Please refer to Section 1.6 for details.

Installation Options
2.2 DECwindows Motif/Hanyu Fonts

Note

Starting with Version 7.1, OpenVMS/Hanyu VAX no longer supports DECwindows Motif/Hanyu Version 1.2 or earlier. To use DECwindows Motif and Chinese characters with OpenVMS/Hanyu VAX Version 7.2, you must install DECwindows Motif/Hanyu Version 1.2-3 or later. Please see *OpenVMS/Hanyu VAX Version 7.2 Release Notes* for details.

3
Installing OpenVMS/Hanyu VAX

This chapter describes how to install the OpenVMS/Hanyu VAX Version 7.2 operating system. Section 3.1.2 contains a step-by-step description of the installation procedure.

3.1 The Installation Procedure

The OpenVMS/Hanyu VAX installation process consists of a series of questions and informational messages.

To abort the installation procedure at any time, press CTRL/Y. However, when you abort the installation procedure, it does not delete files created up to that point. You must delete those files interactively. Appendix C lists the files created by this installation procedure and the directories in which they reside. Note that all files and directories are created under SYS$COMMON.

3.1.1 Invoking VMSINSTAL

To start the installation, invoke the VMSINSTAL procedure from a privileged account, such as the SYSTEM account. VMSINSTAL procedure is in the SYS$UPDATE directory. You use the following syntax to invoke VMSINSTAL procedure:

```
$ @SYS$UPDATE:VMSINSTAL HANYU072 device-name [OPTIONS N]
```

HANYU072
This refers to the OpenVMS/Hanyu VAX Version 7.2 saveset.

device-name
The name of the device on which you plan to mount the media. For example, DKA400: is the device name for a compact disc drive. It is not necessary to use the console drive for this installation. However, if you do use the console drive, you should replace any media you have removed once the installation is completed.

[OPTIONS N]
This portion of the command line invokes the release notes option, allowing you to display or save a copy of the release notes. This portion is optional. If you omit this option, the Release Notes question is omitted from the VMSINSTAL procedure dialog and the release notes are automatically copied to SYS$HELP.

Note that there are several options you can select when you invoke VMSINSTAL procedure. See the OpenVMS Documentation Set on software installation for information on those options.

The following example displays the command to invoke VMSINSTAL procedure to install OpenVMS/Hanyu VAX Version 7.2 from compact disk drive DKA400: and shows the system response:

```
$ @SYS$UPDATE:VMSINSTAL HANYU072 DKA400:[HANYU072.KIT]

         OpenVMS VAX Software Product Installation Procedure V7.2

It is 2-MAR-1999 at 16:22

Enter a question mark (?) at any time for help.
```

If you do not supply either the product name or the device name, VMSINSTAL procedure will prompt you for information later on in the installation process. VMSINSTAL procedure does not prompt you for any options.

3.1.2 Installation Questions

This section discusses the questions that appear during the installation. Appendix A contains a sample installation log showing how the questions can be answered.

Each question in the installation is marked with an asterisk (*) at the beginning of the line. Some questions show the default response in brackets, for example [YES]. If you want to use the default response, press Return.

1. **System backup**

   VMSINSTAL procedure asks if you are satisfied with your system backup using the following question:

   ```
   * Are you satisfied with the backup of your system disk [YES]?
   ```

   You should always back up your system disk before performing an installation. If you are satisfied with the backup of your system disk, press Return. Otherwise, enter NO to discontinue the installation. After backing up your system disk, you can restart the installation.

If you respond YES, VMSINSTAL procedure displays a message showing that the installation has begun. For example:

```
The following products will be processed:
  HANYU V7.2

       Beginning installation of HANYU V7.2 at 16:24
%VMSINSTAL-I-RESTORE, Restoring product save set A ...
```

2. **Choosing Release Notes Options**

   If you specified OPTIONS N in the VMSINSTAL command line, the following release notes options are displayed:

```
  Release Notes Options:
          (1) Display release notes
          (2) Print release notes
          (3) Both 1 and 2
          (4) Copy release notes to SYS$HELP
          (5) Do not display, print or copy release notes
```

   If you select 1, the release notes are displayed on your terminal and are copied to HANYU072.RELEASE_NOTES in SYS$HELP.

   If you select 2, the release notes are queued to SYS$PRINT for printing, and copied to HANYU072.RELEASE_NOTES in SYS$HELP.

   If you select 3, the release notes are displayed on your terminal, queued to SYS$PRINT for printing, and copied to HANYU072.RELEASE_NOTES in SYS$HELP.

   If you select 4, the release notes are copied to HANYU072.RELEASE_ NOTES in SYS$HELP.

   If you select 5, the release notes are not printed, displayed, or copied to SYS$HELP.

   If you did not include the OPTIONS N portion of the VMSINSTAL command line, the following message is displayed:

```
%VMSINSTAL-I-RELMOVED, Product's release notes have been moved to SYS$HELP.
```

3. **Product Authorization Key**

   The installation procedure wants to make sure you have registered and loaded the product authorization key (PAK) of OpenVMS/Hanyu VAX before it checks for its validity. It asks you with the following question:

```
* Does this product have an authorization key registered and loaded?
```

If you answer NO, the installation procedure will stop. If you answer YES but you actually have not loaded the PAK, the Installation Verification Procedure will fail out when it checks the validity of the PAK.

4. **DECwindows Motif/Hanyu fonts**

   The saveset of OpenVMS/Hanyu VAX contains the font files of DECwindows Motif/Hanyu. If you have installed or are planning to install DECwindows Motif/Hanyu V1.2-3 or above to your system, you are recommended to install the fonts by answering YES to the question:

   ```
   * Do you want to install DECwindows Motif /Hanyu fonts [YES]?
   ```

   If you answer NO to the question, the font files will not be installed.

   Note

   If you choose to install the DECwindows Motif/Hanyu fonts, the installation procedure will display a warning message as follows

   ```
   %COPY-W-INCOMPAT,
   VMI$ROOT:[SYSFONT.DECW.75DPI]DECW$FONT_ALIAS_GS.DAT (input) and
   VMI$ROOT:[SYSFONT.DECW.75DPI]DECW$FONT_ALIAS.DAT (output) have
   incompatible attributes
   ```

   This warning message can be safely ignored.

5. **Purge replaced files**

   If you have successfully mounted the media, VMSINSTAL procedure proceeds to restore the saveset A of OpenVMS/Hanyu VAX and move the release notes to SYS$HELP.

   It then asks if you want to purge the files replaced by the installation of OpenVMS/Hanyu VAX as follows:

   ```
   * Do you want to purge files replaced by this installation [YES]?
   ```

   If you answer NO, the old files with the same name in the same directory will remain there. Usually you answer YES to save disk space.

6. **Delete SYS$SPECIFIC files**

   OpenVMS/Hanyu VAX puts its component files in the directories under SYS$COMMON. However, if there are files under SYS$SPECIFIC possessing the same name, those files under SYS$SPECIFIC will be used instead of those under SYS$COMMON. So it is *essential* to delete those SYS$SPECIFIC files in order for OpenVMS/Hanyu VAX to run successfully.

You can have the installation procedure to delete those SYS$SPECIFIC files by answering YES to the question:

```
* Do you want to delete files in SYS$SPECIFIC directory, if found [YES]?
```

If you answer NO to the question, you then need to manually delete those files under SYS$SPECIFIC when their names are in conflict with the files created by this installation procedure. Appendix C lists the files created by this installation procedure.

7. **Choose DTSCS or DRC character set**

   OpenVMS/Hanyu VAX supports DEC Hanyu Character Set, which contains DEC SICGCC and DEC Taiwan Supplemental Character Set (DTSCS), as the default character set. DEC Recommended Character Set (DRC) had been provided in pre-OpenVMS/Hanyu VAX Version 5.4. It is provided as an optional character set in OpenVMS/Hanyu VAX so that applications dependent on DRC can migrate from pre-OpenVMS/Hanyu VAX Version 5.4 to OpenVMS/Hanyu VAX Version 7.2. You will be prompted to choose one of these character sets as follows:

   ```
   * What character set (DTSCS or DRC) will this kit support?
   ```

   "DTSCS" and "DRC" are the only allowed responses. The above prompt will reappear for any invalid response. The selected option will be displayed. For instance, if the DTSCS option is chosen, the message will be

   ```
   This kit supports DTSCS character set
   ```

   Note that DTSCS is recommended.

8. **System shutdown**

   The last question that the installation procedure asks you is:

   ```
   * Will you allow a system shutdown after this product is installed [YES]?
   ```

   Note that before rebooting your system, you should make sure that the command procedure SYS$STARTUP:HSY$STARTUP.COM is executed during system reboot by either putting that command procedure as a SYSMAN startup file, or by adding the line:

   ```
   $ @SYS$STARTUP:HSY$STARTUP.COM
   ```

   to your site-specific startup command procedure SYS$MANAGER:SYSTARTUP_VMS.COM. You are recommended to use the latter method.

3.1.3 Informational Messages

At this point, the installation procedure displays a number of informational messages that report the progress of the installation (refer to the sample installation file in Appendix A for the text of the informational messages that OpenVMS/Hanyu VAX displays).

There is no further question. If the installation procedure has been successful up to this point, VMSINSTAL procedure begins moving files to their target directories, updates the help files, and updates the system library and DCL tables. The following message is displayed:

```
%VMSINSTAL-I-MOVEFILES, Files will now be moved to their target directories...
```

3.1.4 Before completing Installation Procedure

Before fully completing the installation, the installation procedure will run the Installation Verification Procedure to verify the OpenVMS/Hanyu VAX installation.

```
%VMS/HANYU-I-BEGINIVP, beginning 7.2 IVP.
```

3.1.5 Completing the Installation Procedure

The following messages indicate that the entire installation procedure is completed:

```
Installation of HANYU V7.2 completed at 17:01

VMSINSTAL procedure done at 17:07
```

3.2 Error Recovery

If errors occur during the installation, VMSINSTAL procedure displays failure messages.

For descriptions of the error messages generated by those conditions, see the OpenVMS Documentation Set on system messages, recovery procedures and OpenVMS software installation. If you are notified that any of those conditions exists, you should take appropriate actions as described in the message.

4

After Installing OpenVMS/Hanyu VAX

After you have installed the OpenVMS/Hanyu VAX operating system, you need to perform several important tasks to prepare the system for operation. This chapter describes these tasks in the following sections.

4.1 Rebooting The System

If you have chosen to reboot the system after installation, which is the default, the installation procedure will automatically invoke the SHUTDOWN command procedure, and display the following message:

```
%VMSINSTAL-I-SHUTDOWN, This product requires that the system be rebooted.

 SHUTDOWN -- Perform an Orderly System Shutdown
             on node HANVMS
```

If you choose to reboot at a later time, you can use the SHUTDOWN command procedure later as follows:

```
$ @SYS$SYSTEM:SHUTDOWN
```

However, please be reminded that the file SYS$STARTUP:HSY$STARTUP.COM must be executed at startup time. This can be done by one of the following procedures:

Procedure A

By adding the following line to your site-specific VMS startup procedure, SYS$MANAGER:SYSTARTUP_VMS.COM

```
$ @SYS$STARTUP:HSY$STARTUP.COM
```

Note

If you plan to install layered products with Chinese capability, for example, Asian Printing Support for OpenVMS, you should add this

layered product startup command procedure after the above line. Otherwise, the layered product would not startup properly.

Procedure B

This can be done with SYSMAN as

```
$ RUN SYS$SYSTEM:SYSMAN
SYSMAN> STARTUP ADD FILE HSY$STARTUP.COM -
_SYSMAN> /PARAMETER=(P1,P2,P3,P4,P5,P6,P7,P8) -
_SYSMAN> /PHASE=LPBEGIN
```

4.2 Running the Installation Verification Procedure

Once the system is running again, you can invoke a command procedure to verify the OpenVMS/Hanyu VAX installation.

```
$ @SYS$COMMON:[SYSTEST.VMS-HANYU]VMS-HANYU$IVP
```

This Installation Verification Procedure will be invoked by the installation procedure of this version of OpenVMS/Hanyu VAX. Appendix B contains a sample log of the execution of the Installation Verification Procedure.

4.3 Updating Individual Compilers Libraries

Individual compilers have their own libraries. If you upgrade your system to OpenVMS/Hanyu VAX Version 7.2 without re-building the corresponding libraries for individual compilers, those libraries will not automatically reflect the latest contents of the STARLET library. Using new symbols introduced in the latest version of the STARLET library will result in compilation errors. Therefore, after the system is installed or upgraded to OpenVMS/Hanyu VAX, you are recommended to re-install or upgrade the compiler and choose to rebuild its library during installation.

For example, Chinese SMG defines several new literals for supporting character sets in the STARLET library of the system, such as SMGC_ASCII, SMGC_SPEC_GRAPHICS and SMG$C_HANYU. Users can specify the character set parameter in any SMG routine calls with the new literals for processing Chinese characters in their application. Thus, you will have to re-install the compiler and rebuild its library. The program compilation will fail if the compiler library is not updated.

4.4 Determining and Reporting Problems

If you encounter a problem while using OpenVMS/Hanyu VAX Version 7.2, report it to Compaq. Depending on the nature of the problem and the type of support you have, you can take one of the following actions:

- Call Compaq if your software contract or warranty agreement entitles you to telephone support.
- Submit a Software Performance Report (SPR).

Review the Software Product Description (SPD) and Warranty Addendum for an explanation of warranty. If you encounter a problem during the warranty period, report the problem as indicated above or follow alternative instructions provided by Compaq for reporting SPD non-conformance problems.

If you find an error in the OpenVMS/Hanyu Documentation set, fill out and submit the Reader's Comments form to Compaq.

A

OpenVMS/Hanyu VAX Sample Installation

The following is the log of a sample installation.

```
$ @SYS$UPDATE:VMSINSTAL HANYU072 $1$DIA2:[KIT]

        OpenVMS VAX Software Product Installation Procedure V7.2

It is 3-MAR-1999 at 14:05.

Enter a question mark (?) at any time for help.

* Are you satisfied with the backup of your system disk [YES]?

The following products will be processed:

  HANYU V7.2

        Beginning installation of HANYU V7.2 at 14:05

%VMSINSTAL-I-RESTORE, Restoring product save set A ...
%VMSINSTAL-I-RELMOVED, Product's release notes have been moved to SYS$HELP.

******************************************************************************
*                                                                            *
*                    OpenVMS/Hanyu Version 7.2                               *
*                    KIT INSTALLATION PROCEDURE                              *
*                                                                            *
*               COPYRIGHT (C) 1994,1995,1996,1997,1999                       *
*                    COMPAQ COMPUTER CORPORATION                             *
*                HOUSTON TEXAS.  ALL RIGHTS RESERVED.                        *
*                                                                            *
******************************************************************************


        Product:      VMS-UI-HANYU
        Producer:     DEC
        Version:      7.2
        Release Date: 7-MAY-1999

* Does this product have an authorization key registered and loaded? YES
```

OpenVMS/Hanyu VAX Sample Installation

```
  If you have installed or planning to install DECWindows Motif /Hanyu,
  you are recommended to install the DECWindows Motif /Hanyu fonts.

* Do you want to install DECwindows Motif /Hanyu fonts [YES]? NO

* Do you want to purge files replaced by this installation [YES]?

  This kit will be installed under the SYS$COMMON directory of this
  node. If there are files in SYS$SPECIFIC directory and not removed,
  the files will be executed instead of the newly installed ones.

* Do you want to delete files in SYS$SPECIFIC directory, if found [YES]?

  Please choose the character set (DTSCS or DRC) and make sure
  you choose the correct one.

* What Character set (DTSCS or DRC) will this kit support? : DTSCS
  This kit supports DTSCS character set

  CMGR Database already exist on system.
* Install a NEW database or KEEP the old one (NEW or KEEP) [KEEP]:

      #================================================================#
       The file SYS$STARTUP:HSY$STARTUP.COM must be executed at
       startup time.

       This can be done with SYSMAN as
       $ RUN SYS$SYSTEM:SYSMAN
       SYSMAN> STARTUP ADD FILE HSY$STARTUP.COM -
       _SYSMAN> /PARAMETER=(P1,P2,P3,P4,P5,P6,P7,P8) -
       _SYSMAN> /PHASE=LPBEGIN

       OR

       By adding the following line in SYS$MANAGER:SYSTARTUP_VMS.COM
       $ @SYS$STARTUP:HSY$STARTUP.COM

       When the installation is completed, the procedure performs an
       orderly shutdown of the system.  OpenVMS/Hanyu V7.2
       will become available when the system is up again.

      #================================================================#

    To complete the installation of this product, you should reboot
    the system.  If it is not convenient to reboot at this time, then
    enter NO to the following question.

    If you enter NO, the installation procedure will continue.

* Will you allow a system shutdown after this product is installed [YES]? YES
* How many minutes for system shutdown [0]: 5
* Do you want to do an automatic system reboot [YES]? YES

      #================================================================#
        There are NO FURTHER QUESTIONS during the installation and it
        will continue for 10 to 45 minutes...
      #================================================================#
```

```
%VMSINSTAL-I-SYSDIR, This product creates system directory [HSYEXE.VMS072].

    If you intend to execute this layered product on other nodes in your
    VAXcluster, and you have the appropriate software license, you must
    prepare the system-specific roots on the other nodes by issuing the
    following command on each node (using a suitably privileged account):

 $ CREATE /DIRECTORY SYS$SPECIFIC:[HSYEXE.VMS072]/OWNER=[1,4]/PROTECTION
=(S:RWE,O:RWE,G:RE,W:RE)
%VMSINSTAL-I-RESTORE, Restoring product save set B ...

        #============================================================#
         Saving standard files and images for future upgrade ...
        #============================================================#

%COPY-S-COPIED, SYS$COMMON:[SYSEXE]DCL.EXE;1 copied to VMI$ROOT:[HSYEXE.VMS072]
V072$DCL.EXE;2 (229 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSMSG]CLIUTLMSG.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$CLIUTLMSG.EXE;2 (201 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSEXE]SEARCH.EXE;1 copied to VMI$ROOT:[HSYEXE.VMS0
72]V072$SEARCH.EXE;2 (35 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSEXE]SMGBLDTRM.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$SMGBLDTRM.EXE;2 (46 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSEXE]SMGTERMS.TXT;1 copied to VMI$ROOT:[HSYEXE.VM
S072]V072$SMGTERMS.TXT;2 (170 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSEXE]TERMTABLE.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$TERMTABLE.EXE;2 (170 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYS$LDR]FBDRIVER.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$FBDRIVER.EXE;2 (18 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSEXE]TFF$MASTER.DAT;1 copied to VMI$ROOT:[HSYEXE.
VMS072]V072$TFF$MASTER.DAT;2 (134 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSMGR]TFF$STARTUP.COM;27 copied to VMI$ROOT:[HSYEX
E.VMS072]V072$TFF$STARTUP.COM;2 (5 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSHLP]TFF$TFUHELP.HLB;1 copied to VMI$ROOT:[HSYEXE
.VMS072]V072$TFF$TFUHELP.HLB;2 (55 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSLIB]TFFSHR.EXE;1 copied to VMI$ROOT:[HSYEXE.VMS0
72]V072$TFFSHR.EXE;2 (21 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYSEXE]TFU.EXE;1 copied to VMI$ROOT:[HSYEXE.VMS072]
V072$TFU.EXE;2 (32 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYS$LDR]DZDRIVER.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$DZDRIVER.EXE;2 (9 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYS$LDR]YCDRIVER.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$YCDRIVER.EXE;2 (8 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYS$LDR]YEDRIVER.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$YEDRIVER.EXE;2 (9 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYS$LDR]YFDRIVER.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$YFDRIVER.EXE;2 (11 blocks)
%COPY-S-COPIED, SYS$COMMON:[SYS$LDR]YIDRIVER.EXE;1 copied to VMI$ROOT:[HSYEXE.V
MS072]V072$YIDRIVER.EXE;2 (13 blocks)
%VMSINSTAL-I-RESTORE, Restoring product save set C ...
%VMSINSTAL-I-RESTORE, Restoring product save set D ...
%VMSINSTAL-I-RESTORE, Restoring product save set F ...
%VMSINSTAL-I-RESTORE, Restoring product save set G ...
```

OpenVMS/Hanyu VAX Sample Installation

```
        #================================================================#
         Creating libraries ...
        #================================================================#

%LIBRAR-S-INSERTED, module CHARACTER_MANAGER inserted in VMI$ROOT:[HSYHLP]HSYHL
P.HLB;2
%LIBRAR-S-INSERTED, module CMGR inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HDUMP inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HEDT inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HELP inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HMAIL inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HMERGE inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HSORT inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HSYSHR inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HTPU inserted in VMI$ROOT:[HSYHLP]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module Phrase_Input_Utility inserted in VMI$ROOT:[HSYHLP]HS
YHLP.HLB;2
%LIBRAR-S-INSERTED, module CHARACTER_MANAGER inserted in VMI$ROOT:[HSYHLP.HANYU
]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module CMGR inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HDUMP inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HEDT inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HELP inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HMAIL inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HMERGE inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HSORT inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HSYSHR inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module HTPU inserted in VMI$ROOT:[HSYHLP.HANYU]HSYHLP.HLB;2
%LIBRAR-S-INSERTED, module Phrase_Input_Utility inserted in VMI$ROOT:[HSYHLP.HA
NYU]HSYHLP.HLB;2

        #================================================================#
         Moving files to destination directories and searching SYS$SPECIFIC
        #================================================================#

%CREATE-I-CREATED, $1$DIA1:[SYS0.SYSUPD.HANYU072]AVMS$TEMPSPEC.DAT;1 created
%CREATE-I-CREATED, $1$DIA1:[SYS0.SYSUPD.HANYU072]AVMS$TEMPDELETE.COM;1 created
%DELETE-I-FILDEL, $1$DIA1:[SYS0.SYSUPD.HANYU072]AVMS$TEMPSPEC.DAT;2 deleted (0
blocks)
%DELETE-I-FILDEL, $1$DIA1:[SYS0.SYSUPD.HANYU072]AVMS$TEMPSPEC.DAT;1 deleted (0
blocks)
%DELETE-I-FILDEL, $1$DIA1:[SYS0.SYSUPD.HANYU072]AVMS$TEMPDELETE.COM;2 deleted (
4 blocks)
%DELETE-I-FILDEL, $1$DIA1:[SYS0.SYSUPD.HANYU072]AVMS$TEMPDELETE.COM;1 deleted (
0 blocks)
%DELETE-I-TOTAL, 4 files deleted (4 blocks)
%RENAME-I-RENAMED, VMI$SPECIFIC:[SYSEXE]TEMPMODPARAMS.DAT;1 renamed to VMI$SPEC
IFIC:[SYSEXE]MODPARAMS.DAT;2

%CREATE-I-CREATED, $1$DIA1:[SYS0.SYSUPD.HANYU072]HANYUSTATE.MAR;1 created
%VMSINSTAL-I-MOVEFILES, Files will now be moved to their target directories...

%VMS/HANYU-I-BEGINIVP, beginning 7.2 IVP.
```

OpenVMS/Hanyu VAX Sample Installation

```
****************************************************************************
*                                                                          *
*                       OpenVMS/Hanyu VAX V7.2                             *
*                  INSTALLATION VERIFICATION PROCEDURE                     *
*                                                                          *
*             COPYRIGHT (C) 1993,1994,1995,1996,1997,1999                  *
*                                                                          *
*                     COMPAQ COMPUTER CORPORATION                          *
*                  HOUSTON TEXAS.  ALL RIGHTS RESERVED.                    *
*                                                                          *
****************************************************************************

        Starting OpenVMS/Hanyu VAX IVP ...
%VMS/HANYU-I-ENDIVP, 7.2 IVP completed successfully.

        Installation of HANYU V7.2 completed at 14:20

%VMSINSTAL-I-SHUTDOWN, This product requires that the system be rebooted.

        SHUTDOWN -- Perform an Orderly System Shutdown
                    on node AVMS

Do you really want to shutdown node AVMS [NO]?

        VMSINSTAL procedure done at 14:24
```

B

OpenVMS/Hanyu VAX Sample Installation Verification Procedure

This appendix contains a sample of the Installation Verification Procedure (IVP). Refer to Chapter 4 for information about running the IVP.

```
$ @SYS$COMMON:[SYSTEST.VMS-HANYU]VMS-HANYU$IVP

*****************************************************************************
*                                                                           *
*                        OpenVMS/Hanyu VAX V7.2                             *
*                  INSTALLATION VERIFICATION PROCEDURE                      *
*                                                                           *
*             COPYRIGHT (C) 1993,1994,1995,1996,1997,1999                   *
*                                                                           *
*                     COMPAQ COMPUTER CORPORATION                           *
*                  HOUSTON TEXAS.  ALL RIGHTS RESERVED.                     *
*                                                                           *
*****************************************************************************

         Starting OpenVMS/Hanyu VAX IVP ...

         OpenVMS/Hanyu VAX IVP completed successfully.

$
```

C

OpenVMS/Hanyu VAX Software Components and Defined System Logical Names

The OpenVMS/Hanyu VAX installation procedure installs a number of files on your system. Table C–1 lists the names of all the files installed in the directories under SYS$COMMON when OpenVMS/Hanyu VAX is installed.

Table C–1 Component File List

Directory	File	Change
[DECW$DEFAULTS.SYSTEM.ZH_TW]	HEVE$WIDGETS_MOTIF.UID	New
[HSYEXE.EXAMPLE]	CALLASMG$C.C	New
[HSYEXE.EXAMPLE]	CALLASMG$FORTRAN.FOR	New
[HSYEXE.EXAMPLE]	DATETIME.C	New
[HSYEXE.EXAMPLE]	EXAM31.DAT	New
[HSYEXE.EXAMPLE]	EXAM32.DAT	New
[HSYEXE.EXAMPLE]	EXAMPLE.B32	New
[HSYEXE.EXAMPLE]	POET.DAT	New
[HSYEXE.EXAMPLE]	SAMPLE.BAS	New
[HSYEXE.EXAMPLE]	SAMPLE.C	New
[HSYEXE.EXAMPLE]	SAMPLE.COB	New
[HSYEXE.EXAMPLE]	SAMPLE.FOR	New
[HSYEXE.EXAMPLE]	SAMPLE.MAR	New
[HSYEXE.EXAMPLE]	SAMPLE.PAS	New
[HSYEXE.EXAMPLE]	SAMPLE.PLI	New

(continued on next page)

Table C–1 (Cont.) Component File List

Directory	File	Change
[HSYEXE.EXAMPLE]	SAMPLE_HSYSHR.C	New
[HSYEXE.EXAMPLE]	SAMPLE_MERGE.C	New
[HSYEXE.EXAMPLE]	SAMPLE_SORT1.FOR	New
[HSYEXE.EXAMPLE]	SAMPLE_SORT2.FOR	New
[HSYEXE.EXAMPLE]	TEXT.IN	New
[HSYEXE.HANYU072]	EDIT.CLD	Replace
[HSYEXE.HANYU072]	EDIT_EN.HLP	Replace
[HSYEXE.HANYU072]	SORT.CLD	Replace
[HSYEXE.HANYU072]	SORTMERGE_DCL.HLP	Replace
[HSYEXE]	CMGR.EXE	New
[HSYEXE]	FONTHANDL.EXE	New
[HSYEXE]	HANYUGEN.EXE	New
[HSYEXE]	HDUMP.EXE	New
[HSYEXE]	HEDT.EXE	New
[HSYEXE]	HMAIL.EXE	New
[HSYEXE]	HSY$CHARACTER_INDEX.DAT	New
[HSYEXE]	HSY$CHARACTER_MASTER_ INDEX.DAT	New
[HSYEXE]	HSY$DECHANYU_CODE_INFO.DAT	New
[HSYEXE]	HSY$GLYPH_24X24_USER.GDB	New
[HSYEXE]	HSY$GLYPH_32X32_USER.GDB	New
[HSYEXE]	HSY$GLYPH_40X40_USER.GDB	New
[HSYEXE]	HSY$HANYU_SOFT.GDB	New
[HSYEXE]	HSY$HEI_24X24_USER.GDB	New
[HSYEXE]	HSY$HEI_32X32_USER.GDB	New
[HSYEXE]	HSY$HEI_40X40_USER.GDB	New
[HSYEXE]	HSY$HEI_CHARACTER_INDEX.DAT	New
[HSYEXE]	HSY$HEI_CHARACTER_INDEX.DAT	New
[HSYEXE]	HSY$HEI_SORTDB.CDB	New

(continued on next page)

Table C–1 (Cont.) Component File List

Directory	File	Change
[HSYEXE]	HSY$HEI_SORT_INDEX.DAT	New
[HSYEXE]	HSY$INIT.EXE	New
[HSYEXE]	HSY$PHRASE.DAT	New
[HSYEXE]	HSY$PHRASE_CLASS.DAT	New
[HSYEXE]	HSY$SORTDB.CDB	New
[HSYEXE]	HSY$SORT_INDEX.DAT	New
[HSYEXE]	HSY$SUNG_24X24_USER.GDB	New
[HSYEXE]	HSY$SUNG_32X32_USER.GDB	New
[HSYEXE]	HSY$SUNG_40X40_USER.GDB	New
[HSYEXE]	HSY$SUNG_CHARACTER_INDEX.DAT	New
[HSYEXE]	HSY$SUNG_SORTDB.CDB	New
[HSYEXE]	HSY$SUNG_SORT_INDEX.DAT	New
[HSYEXE]	HSY$TAIWAN_SPECIFIC.DAT	New
[HSYEXE]	HTPU.EXE	New
[HSYEXE]	MAILEDIT_TAI.COM	New
[HSYEXE]	PHRASE.EXE	New
[HSYEXE]	RECOVER.COM	New
[HSYEXE]	WWPPS.EXE	New
[HSYHLP.HANYU]	CMGREDIT.HLB	New
[HSYHLP.HANYU]	CMGRHELP.HLB	New
[HSYHLP.HANYU]	HANYUGEN.HLB	New
[HSYHLP.HANYU]	HEDTHELP.HLB	New
[HSYHLP.HANYU]	HEVE$HELP.HLB	New
[HSYHLP.HANYU]	HEVE$KEYHELP.HLB	New
[HSYHLP.HANYU]	HMAILHELP.HLB	New
[HSYHLP.HANYU]	HTPUHELP.HLB	New
[HSYHLP]	CMGREDIT.HLB	New
[HSYHLP]	CMGRHELP.HLB	New
[HSYHLP]	HANYUGEN.HLB	New

(continued on next page)

Table C–1 (Cont.) Component File List

Directory	File	Change
[HSYHLP]	HEDTHELP.HLB	New
[HSYHLP]	HEVE$HELP.HLB	New
[HSYHLP]	HEVE$KEYHELP.HLB	New
[HSYHLP]	HMAILHELP.HLB	New
[HSYHLP]	HTPUHELP.HLB	New
[SYS$LDR]	ASDRIVER.EXE	New
[SYS$LDR]	DZDRIVER.EXE	Replace
[SYS$LDR]	FBDRIVER.EXE	Replace
[SYS$LDR]	FHDRIVER.EXE	New
[SYS$LDR]	HNDRIVER.EXE	New
[SYS$LDR]	YCDRIVER.EXE	Replace
[SYS$LDR]	YEDRIVER.EXE	Replace
[SYS$LDR]	YFDRIVER.EXE	Replace
[SYS$LDR]	YIDRIVER.EXE	Replace
[SYS$STARTUP]	HSY$CONFIG.COM	New
[SYS$STARTUP]	HSY$STARTUP.COM	New
[SYS$STARTUP]	HSYHLPSTARTUP.COM	New
[SYSEXE]	DCL.EXE	Replace
[SYSEXE]	SEARCH.EXE	Replace
[SYSEXE]	SMGBLDTRM.EXE	Replace
[SYSEXE]	SMGTERMS.TXT	Replace
[SYSEXE]	TERMTABLE.EXE	Replace
[SYSEXE]	TFF$MASTER.DAT	Replace
[SYSEXE]	TFU.EXE	Replace
[SYSFONT.WWPPS]	ANGSANAUPC-BOLD.	New
[SYSFONT.WWPPS]	ANGSANAUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	ANGSANAUPC-ITALIC.	New
[SYSFONT.WWPPS]	ANGSANAUPC-LIGHT.	New
[SYSFONT.WWPPS]	CORDIAUPC-BOLD.	New

(continued on next page)

Table C–1 (Cont.) Component File List

Directory	File	Change
[SYSFONT.WWPPS]	CORDIAUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	CORDIAUPC-ITALIC.	New
[SYSFONT.WWPPS]	CORDIAUPC-LIGHT.	New
[SYSFONT.WWPPS]	EUCROSIAUPC-BOLD.	New
[SYSFONT.WWPPS]	EUCROSIAUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	EUCROSIAUPC-ITALIC.	New
[SYSFONT.WWPPS]	EUCROSIAUPC-LIGHT.	New
[SYSFONT.WWPPS]	FREESIAUPC-BOLD.	New
[SYSFONT.WWPPS]	FREESIAUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	FREESIAUPC-ITALIC.	New
[SYSFONT.WWPPS]	FREESIAUPC-LIGHT.	New
[SYSFONT.WWPPS]	HEI-GB2312-80.CSDATA	New
[SYSFONT.WWPPS]	HEI-LIGHT-CNS11643-1.CSDATA	New
[SYSFONT.WWPPS]	HEI-LIGHT-CNS11643-2.CSDATA	New
[SYSFONT.WWPPS]	IRISUPC-BOLD.	New
[SYSFONT.WWPPS]	IRISUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	IRISUPC-ITALIC.	New
[SYSFONT.WWPPS]	IRISUPC-LIGHT.	New
[SYSFONT.WWPPS]	JASMINEUPC-BOLD.	New
[SYSFONT.WWPPS]	JASMINEUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	JASMINEUPC-ITALIC.	New
[SYSFONT.WWPPS]	JASMINEUPC-LIGHT.	New
[SYSFONT.WWPPS]	KODCHIANGUPC-BOLD.	New
[SYSFONT.WWPPS]	KODCHIANGUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	KODCHIANGUPC-ITALIC.	New
[SYSFONT.WWPPS]	KODCHIANGUPC-LIGHT.	New
[SYSFONT.WWPPS]	LILYUPC-BOLD.	New
[SYSFONT.WWPPS]	LILYUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	LILYUPC-ITALIC.	New

(continued on next page)

Table C–1 (Cont.) Component File List

Directory	File	Change
[SYSFONT.WWPPS]	LILYUPC-LIGHT.	New
[SYSFONT.WWPPS]	MUNJO.CSDATA	New
[SYSFONT.WWPPS]	SUNG-LIGHT-CNS11643-1.CSDATA	New
[SYSFONT.WWPPS]	SUNG-LIGHT-CNS11643-2.CSDATA	New
[SYSFONT.WWPPS]	WATERLILYUPC-BOLD.	New
[SYSFONT.WWPPS]	WATERLILYUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	WATERLILYUPC-ITALIC.	New
[SYSFONT.WWPPS]	WATERLILYUPC-LIGHT.	New
[SYSFONT.WWPPS]	XISONG-GB2312-80.CSDATA	New
[SYSFONT.WWPPS]	YUCCAUPC-BOLD.	New
[SYSFONT.WWPPS]	YUCCAUPC-BOLDITALIC.	New
[SYSFONT.WWPPS]	YUCCAUPC-ITALIC.	New
[SYSFONT.WWPPS]	YUCCAUPC-LIGHT.	New
[SYSHLP.HANYU]	TFF$TFUHELP.HLB	New
[SYSHLP]	HANYU072.RELEASE_NOTES	New
[SYSHLP]	TFF$TFUHELP.HLB	Replace
[SYSHLP]	WWPPSHLP.HLB	New
[SYSLIB]	CMGRDISPSHR.EXE	New
[SYSLIB]	CMGRSHR.EXE	New
[SYSLIB]	HEDTSHR.EXE	New
[SYSLIB]	HEVE$SECTION.TPU$SECTION	New
[SYSLIB]	HEVE$WIDGETS_MOTIF.UID	New
[SYSLIB]	HEVE.DAT	New
[SYSLIB]	HMAILSHR.EXE	New
[SYSLIB]	HMAILSHRP.EXE	New
[SYSLIB]	HSMGSHR.EXE	New
[SYSLIB]	HSYSHR.EXE	New
[SYSLIB]	HTPU$CCTSHR.EXE	New
[SYSLIB]	HTPU$DEBUG.TPU	New

(continued on next page)

Table C–1 (Cont.) Component File List

Directory	File	Change
[SYSLIB]	HTPU$MOTIFSHR.EXE	New
[SYSLIB]	HTPU.DAT	New
[SYSLIB]	HTPUSHR.EXE	New
[SYSLIB]	LATSYM$SETUP.EXE	New
[SYSLIB]	SOR4BYTEDICT.EXE	New
[SYSLIB]	SORTAIDICT.EXE	New
[SYSLIB]	SORTDTYPE.EXE	New
[SYSLIB]	TFFSHR.EXE	Replace
[SYSLIB]	WWPPS.PCF	New
[SYSMGR]	TFF$STARTUP.COM	Replace
[SYSMSG.HANYU]	CLIUTLMSG.EXE	New
[SYSMSG.HANYU]	CMGRMSG.EXE	New
[SYSMSG.HANYU]	HDUMPMSG.EXE	New
[SYSMSG.HANYU]	HMAILMSG.EXE	New
[SYSMSG.HANYU]	HTPUMSG.EXE	New
[SYSMSG.HANYU]	SORTMSG.EXE	New
[SYSMSG]	CLIUTLMSG.EXE	Replace
[SYSMSG]	CMGRMSG.EXE	New
[SYSMSG]	HDUMPMSG.EXE	New
[SYSMSG]	HEDTMSG.EXE	New
[SYSMSG]	HMAILMSG.EXE	New
[SYSMSG]	HTPUMSG.EXE	New
[SYSMSG]	SORTMSG.EXE	New
[SYSTEST.VMS-HANYU]	AVMSIVP.EXE	New
[SYSTEST.VMS-HANYU]	VMS-HANYU$IVP.COM	New

OpenVMS/Hanyu VAX Software Components and Defined System Logical Names

Table C–2 lists the system logical names defined by the OpenVMS/Hanyu VAX startup procedure.

Table C–2 Defined System Logical Names

Logical Name	Value
CMGR$MASTER	HSY$SYSTEM:HSY$CHARACTER_MASTER_INDEX
HSY$EXAMPLE	SYS$SYSROOT:[HSYEXE.EXAMPLE]
HSY$HELP	SYS$SYSROOT:[HSYHLP.HANYU], SYS$SYSROOT:[HSYHLP]
HSY$LIBRARY	SYS$LIBRARY
HSY$SYSTEM	SYS$SYSROOT:[HSYEXE]
HTPU$SECTION	HEVE$SECTION
HTPU$JOURNAL	SYS$SCRATCH
SYS$HELP	SYS$SYSROOT:[SYSHLP.HANYU], SYS$SYSROOT:[SYSHLP]
SYS$MESSAGE	SYS$SYSROOT:[SYSMSG.HANYU], SYS$SYSROOT:[SYSMSG]